

**Mergable Cell Listbox  
Overview/Demo Documentation  
Version 1.0**

**Karen Atkocius  
keatk@verizon.net**

## Overview

The listbox subclasses classes in this project add several useful new features to the standard REALStudio listbox. In my past life often had to create tables to display/report/manage data. My tool of choice was a spreadsheet as it was both easy to do calculations and lay out tables that were easy to read/understand. One of the most useful tools for creating easily readable layouts was the ability to merge cells to organize data logically, clearly. and use space efficiently.

That was what I missed most when I tried to use the REALStudio listbox for data presentation. This project is the result of that frustration. The main focus of these classes is to provide as comprehensive as possible support for merging cells across rows and columns to be able to do the type of data presentation one can do in Excel.

An area of merged cells for the most part is treated as a single cell having the coordinates of the top left cell of the group. See the API documentation for details. When a row is selected all multi-row merged cells which intersect it are highlighted. Be aware that supporting this highlighting in a consistent manor necessitates a lot of listbox redrawing.

The features specific to merged cells are:

- 1) Merging and unmerging of cells across both rows and columns
- 2) Column resizing across merged areas
- 3) Editing merged cells
- 4) Rows may be inserted or deleted within merged area that cross rows. The merged area is either expanded or contracted as expected
- 5) Rows which are folders may be merged as long as the folder is the top row or last row

In addition other useful features are also included:

- 1) Specifying a background color as well as alternating row colors via the property pane
- 2) Support for Multi-line text a cell:
  - Text Wrapping. Does **NOT** simply use g.DrawString with the WrapWidth parameter. Only displays lines that are fully visible and if all text is not displayed last line will have an ellipsis even if that line fits in the cell (ends a paragraph)
  - Editing Multi-Line text (can use return key to start new line )
  - May specifying line spacing and line by line horizontal alignment
  - May optionally use a vertical scrollbar for in cell editing
- 3) Allows aligning text (single or multi-line) vertically as well as horizontally
- 4) Provides enhanced cell text attribute and border assignment methods
- 5) Hierarchical Listbox support:
  - Uses the standard RealStudio listbox hierarchical API. Does not force a specific data structure
  - Optionally draws lines connecting folders and their children
  - Enhanced UI for Expanding/Collapsing Folders:
    - Option Click on a closed disclosure widget will open all sublevels
    - SpaceBar toggles disclosure widget. If closed Option-SpaceBar will open all sublevels
    - Option-UpArrow closes an open folder. Option-DownArrow opens a folder.
    - If closed, Shift-Option-DownArrow will open all sublevels
  - Provides methods to:
    - determine if a row is a folder
    - return the indent level of a row
    - open all sublevels of a folder
    - close all open folders
    - inhibit the drawing of the horizontal connector line to a child row. Useful for visual grouping when related data is presented in multiple child rows at the same indent level. In other words data for one logical node is displayed in multiple consecutive rows. (See Lot Testing Demo)

All features work on OS X and Windows (only XP tested).

At this time on Linux the CellBorder settings do not work as expected . This may be worked around by drawing borders in the paint events. Also drawing connecting lines in hierarchical listboxes does not work for cells merged across rows. In addition on Linux, the CellPaint events can sometime draw outside of their cells and outside the listbox (a REALStudio bug), particularly when resizing columns or the listbox. Also on Linux resizing can also be very sluggish and unattractive visually.

Merged cells may be able to be used in Linux in some specific cases, however the potential for visual glitches is high. Ubuntu screen screenshots are included for all demo screens.


The demos included were created to test/debug the classes, as well as show possible uses and demonstrate how to code them. This assumes you have good understanding of the standard REALStudio listbox API.

I tried to design the extensions to be as consistent as possible with REAL's listbox API design (which is very flexible but not simple) as I could. However because a merged cell may cross both rows and columns one must take that into consideration when coding using the standard listbox APIs.

For example if a cell is merged across rows, in an event, just because listbox.Selected(row) is false does not mean a cell the row intersects is not selected! You would need to check using the new method SelectedCell(row,column) to be sure.

## The Demo Application

When you startup the demo app you will see a window showing the demo options:



There are 4 Demo windows. The are accessible either through this dialog or through the Window menu.

### 1) Lot Testing Results

The “Lot testing Results” screen is meant to show how lot testing could be presented using merged cells and is shown below:

Lot Testing Results

Lot Testing Results For Product XYZ

Lot: 0470-0370

Jun 8, 2010

PASS

Lot: 0129-0796

May 24, 2010

PASS

Test: Post Reconstruction Particle Size

Test: Suspension Gas

Lot: 0403-2831

May 27, 2010

PASS

Lot: 0192-2025

Jun 13, 2010

PASS

Lot: 0229-160X

Jun 16, 2010

PASS

Test: Post Reconstruction Particle Size

Results Summary (gm)

Analyst:

Vial 1

Vial 2

Vial 3

Vial 4

Average

% RSD

Karen Somebody

2.449

2.368

2.429

2.390

2.409

1.53%

Details

PASS

PASS

PASS

PASS

2.409

1.53%

Comments

Replicates

2.449

2.363

2.428

2.382

2.447

2.360

2.424

2.384

None

% RSD

0.10%

0.46%

0.25%

0.53%

Test: Suspension Gas

Lot: 0446-110U

May 5, 2010

PASS

Lot: 0349-0416

Jun 26, 2010

PASS

Lot: 0078-143R

May 5, 2010

PASS

Lot Testing Results

Lot Testing Results For Product XYZ

Lot: 0476-098D

Thu, Apr 29, 2010

FAIL

Lot: 0427-248Y

Wed, May 26, 2010

PASS

Test: Post Reconstruction Particle Size

Test: Suspension Gas

Lot: 0209-108H

Thu, May 06, 2010

PASS

Lot: 0294-324H

Mon, Jul 05, 2010

FAIL

Lot: 0344-127Z

Sun, May 23, 2010

PASS

Test: Post Reconstruction Particle Size

Results Summary (gm)

Analyst:

Vial 1

Vial 2

Vial 3

Vial 4

Average

% RSD

Karen Somebody

2.449

2.360

2.429

2.390

2.409

1.53%

Details

PASS

PASS

PASS

PASS

2.409

1.53%

Comments

Replicates

2.449

2.360

2.428

2.382

2.447

2.360

2.424

2.384

None

% RSD

0.10%

0.46%

0.25%

0.53%

Test: Suspension Gas

Lot: 0218-0801

Sat, Jun 26, 2010

PASS

Lot: 0017-229P

Tue, May 18, 2010

PASS

Lot: 0408-112E

Wed, May 05, 2010

PASS

Lot Testing Results

Lot Testing Results For Product XYZ

Lot: 0346-101W

Mon, Jul 05, 2010

PASS

Lot: 0006-241B

Mon, Jul 05, 2010

PASS

Test: Post Reconstruction Particle Size

Test: Suspension Gas

Lot: 0158-154P

Wed, Apr 28, 2010

FAIL

Lot: 0466-132V

Thu, Jun 10, 2010

FAIL

Lot: 0236-031D

Fri, Jun 11, 2010

PASS

Test: Post Reconstruction Particle Size

Results Summary (gm)

Analyst:

Vial 1

Vial 2

Vial 3

Vial 4

Average

% RSD

Karen Somebody

2.449

2.368

2.429

2.390

2.409

1.53%

Details

PASS

PASS

PASS

PASS

2.409

1.53%

Comments

Replicates

2.449

2.363

2.428

2.382

2.447

2.360

2.424

2.384

None

% RSD

0.10%

0.46%

0.25%

0.53%

Test: Suspension Gas

Lot: 0118-292D

Mon, Jun 14, 2010

PASS

Lot: 0450-229Y

Tue, Jun 22, 2010

PASS

Lot: 0077-090H

Thu, Apr 29, 2010

PASS

Each lot has 4 level each with more detail than the last. Merged cells are used to visually group the data within each level to maximize screen usage and improve readability for busy end user. Note that option clicking on a closed disclosure widget will open all of it's sublevels. This is not specific to the screen but supported generally by the base class.


Normally when node lines are used there are lines connecting a folder to each of it's child rows. In the case of merged cells there is only one connect to the top merged row.

But notice that there is no connection from the "Test: Post Reconstitution ..." to the child "Analyst: ..." or from the "Details" folder to the child "Replicates". This is because of the use of the InhibitConnector method which prevented them from being drawn. This gives a better visual grouping in this case.

At the lowest level, the comments fields is editable. Clicking on it will allow you to enter text directly into it. The window (and so the listbox) is resizable.

## 2) Calendar

This demo of a daily schedule planner app and is more extensive. Examples shown below:



Here the listbox selection type is set to multi-line and visually then selection is by cell. The mouse or the arrow keys may be used for navigation. Multiple selections are made using the shift modifier key with the keyboard or mouse. Drag selection can also be used. Only contiguous multiple cell selections are only allowed within a single column (day). Using the Control Key to make discontiguous selections in not allowed.



A selected cell or group if cells may used to create new events or extend existing events by either hitting return, selecting "Extend/Merge" or "New" from the Event menu , by right clicking and selecting the desired option from the contextual menu or using the appropriate menu shortcut. If a single event is selected hitting return or using the Event Menu (or contextual menu option) allows you to edit the text. Deleting an event may only be done via either of the menus mentioned or the menu shortcut.

Selected cells may be "tagged" with a predefined color via the "Tag" submenu of the Event or contextual menu or the menu shortcut (MenuModifierKey + 1-8 )

Columns are resizable, as is the window and with it the listbox.

### 3) Testing/Picture Demo Window

This is the window that was used to debug the listbox. It shows a picture as the background of a merged cell. The primary focus was to test/debug the visual aspects of cell merging, including selection, column resizing, editing, text wrapping, text alignment and checkboxes during development and merged folders. Examples from each OS are shown below:




The popup menus allows changing test alignment and line spacing. The text fields allow changing row height and font size. Enter a value and hit return. The “Add Folder” button ad a folder, and merges it with another row. Clicking on the resulting widget shows child rows, some of which are also merged. This is shown in the OS X Screen shot.

If you edit the merged cell at row 7 column 4, the cell will have a vertical scrollbar while editing. The appearance of a scrollbar depends on the setting of the VerticalScrollBar property the TextArea subclass instance(s) placed on the listbox and the new event EditMode Event. See API documentation for details. The use of the details could have been hidden by the use of a Container control, but this would have limited use to Pro and Enterprise versions of REALStudio. Also this approach

#### 4) Text Flow

This is to demonstrate the text wrapping utility routines. While not part of the listbox classes they may be used in the paint events. However they can also be used to ‘flow’ a single large string into multiple rectangular areas for layout type text drawing. This is an example of that use:



The popup menus may be used to change the vertical alignment within each block, the line by line horizontal alignment of the text and the line spacing. The window may be resized somewhat changing the size of blocks, and the text will flow into the new dimensions.

software and associated documentation files (the “Software”), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR